

ATR3 (Accums Transfer File) Labor Funds Data Dictionary

Field ID	FIELD NAME	COBOL PICTURE	COLUMN	JUSTIFY	INITIAL	REQUIRED/ OPTIONAL	DEFINITION/VALID VALUES
ATR3 HEADER		197 BYTES	POSITION 1				
A	ATR3-REC-INDICATOR	PIC X(01)	001-001	na	na	R	Valid Value = H (for Header)
B	ATR3-HDR-LABOR-FUND-NAME	PIC X(09)	002-010	Left	Spaces	R	Will store labor fund ID: e.g. LABOR002. Format = LABORXXX
C	ATR3-RUN-DATE	PIC 9(08)	011-018	Right	Zeros	R	Date the ATR3 was created. Format = MMDDCCYY
D	ATR3-HDR-VERSION	PIC X(02)	019-020	Right	Spaces	R	Field should contain value 02
E	ATR3-HDR-Filler	PIC X(177)	021-197	Right	Spaces	na	Filler, value spaces
ATR3 DATA FIELDS		197 BYTES	POSITION 1				
1	ATR3-SUBSCRIBER-UID	PIC X(09)	001-009	Left	Spaces	R	Subscriber unique identification number.
2	ATR3-RELATIONSHIP	PIC X(01)	010-010	Left	Spaces	R	Defines the relationship to the subscriber:
							1= Member Accum. 2= Spouse Accum. 3=Dependent
3	ATR3-PAT-LAST-NAME	PIC X(15)	011-025	Left	Spaces	R	Last name of patient

ATR3 (Accums Transfer File) Labor Funds Data Dictionary

Field ID	FIELD NAME	COBOL PICTURE	COLUMN	JUSTIFY	INITIAL	REQUIRED/ OPTIONAL	DEFINITION/VALID VALUES
4	ATR3-PAT-FIRST-NAME	PIC X(10)	026-035	Left	Spaces	R	First name of patient
5	ATR3-PAT-MIDDLE-NAME	PIC X(01)	036-036	na	Spaces	O	Middle initial of patient; space if no middle name
6	ATR3-PAT-DATE-OF-BIRTH	PIC 9(08)	037-044	Right	Zeros	R	Patient's date of birth; Format = MMDDCCYY
7	ATR3-PAT-SEX	PIC X(01)	045-045	na	na	R	Patients sex; M = Male, F = Female
8	ATR3-ACCUM-BENEFIT-PERIOD	PIC X(02)	046-047	Left	na	R	Defines the time frame of the accumulator See Benefit Periods Tab for values
9	ATR3-ACCUM-BEN-PER-DT	PIC 9(08)	048-055	Right	Zeros	R	Defines the effective date of accumulator:
							Date that represents the beginning date of the accum benefit period. For lifetime max, submit as '01010001'
10	ATR3-ACCUM-TYPE	PIC X(02)	056-057	Left	na	R	Defines the accumulator type See Benefit Type Tab for values
11	ATR3-ACCUM-BENEFIT	PIC X(02)	058-059	Left	na	R	Defines the benefit accumulated.
							See your account tailored Accum Benefit Sheet for values

ATR3 (Accums Transfer File) Labor Funds Data Dictionary

Field ID	FIELD NAME	COBOL PICTURE	COLUMN	JUSTIFY	INITIAL	REQUIRED/ OPTIONAL	DEFINITION/VALID VALUES
12	ATR3-ACCUM-VALUE-QUALIFIER	PIC X(02)	060-061	Left	na	R	Defines the unit of measure for the accumulator See Value Qualifer Tab for values
13	ATR3-ACCUM-AMOUNT	PIC S9(7)V99	062-070	Right	Zeros	R	Defines the amount accumulated for the benefit
14	ATR3-ACCUM-PERCENT-LEVEL	PIC S9V99	071-073	Right	Zeros	Conditionally required	Defines percent level of accumulated value
							Accumulator percent level limits - only if Benefit is for Coinsurance or OutOfPocket, otherwise leave blank
							Percent level in decimal form (e.g. 0.80 for 80%)
15	ATR3-MEMB-GROUP-NUMBER	PIC X(9)	074-082	Right	Zeros	R	Identifies BCBS group number of the member.
16	ATR3-REJECT1	PIC X(1)	083-083	Right	Spaces	na	Defines Reject Code for Field ID 1 - SUBSCRIBER-UID. V=Valid, I=Invalid
17	ATR3-REJECT2	PIC X(1)	084-084	Right	Spaces	na	Defines Reject Code for Field ID 2 - RELATIONSHIP. V=Valid, I=Invalid
18	ATR3-REJECT3	PIC X(1)	085-085	Right	Spaces	na	Defines Reject Code for Field ID 3 - PAT-LAST-NAME. V=Valid, I=Invalid
19	ATR3-REJECT4	PIC X(1)	086-086	Right	Spaces	na	Defines Reject Code for Field ID 4 - PAT-FIRST-NAME. V=Valid, I=Invalid
20	ATR3-REJECT5	PIC X(1)	087-087	Right	Spaces	na	Defines Reject Code for Field ID 5 - PAT-MIDDLE-NAME. V=Valid, I=Invalid
21	ATR3-REJECT6	PIC X(1)	088-088	Right	Spaces	na	Defines Reject Code for Field ID 6 - PAT-DATE-OF-BIRTH. V=Valid, I=Invalid
22	ATR3-REJECT7	PIC X(1)	089-089	Right	Spaces	na	Defines Reject Code for Field ID 7 - PAT-SEX. V=Valid, I=Invalid

ATR3 (Accums Transfer File) Labor Funds Data Dictionary

Field ID	FIELD NAME	COBOL PICTURE	COLUMN	JUSTIFY	INITIAL	REQUIRED/ OPTIONAL	DEFINITION/VALID VALUES
23	ATR3-REJECT8	PIC X(1)	090-090	Right	Spaces	na	Defines Reject Code for Field ID 8 - ACCUM-BENEFIT-PERIOD. V=Valid, I=Invalid
24	ATR3-REJECT9	PIC X(1)	091-091	Right	Spaces	na	Defines Reject Code for Field ID 9 - ACCUM-BEN-PER-DT. V=Valid, I=Invalid
25	ATR3-REJECT10	PIC X(1)	092-092	Right	Spaces	na	Defines Reject Code for Field ID 10 - ACCUM-TYPE. V=Valid, I=Invalid
26	ATR3-REJECT11	PIC X(1)	093-093	Right	Spaces	na	Defines Reject Code for Field ID 11 - ACCUM-BENEFIT. V=Valid, I=Invalid
27	ATR3-REJECT12	PIC X(1)	094-094	Right	Spaces	na	Defines Reject Code for Field ID 12 - ACCUM-VALUE-QUALIFIER. V=Valid, I=Invalid
28	ATR3-REJECT13	PIC X(1)	095-095	Right	Spaces	na	Defines Reject Code for Field ID 13 - ACCUM-AMOUNT. V=Valid, I=Invalid
29	ATR3-REJECT14	PIC X(1)	096-096	Right	Spaces	na	Defines Reject Code for Field ID 14 - ACCUM-PERCENT-LEVEL. V=Valid, I=Invalid
30	ATR3-REJECT15	PIC X(1)	097-097	Right	Spaces	na	Defines Reject Code for Field ID 15 - MEMB-GROUP-NUMBER. V=Valid, I=Invalid
ZZ	ATR3-FILLER	PIC X(100)	098-197	Left	Spaces	na	Filler; value spaces
NO Footer Required							